

Installation auf Hetzner

Auf Hetzner-Server:

```
ssh hetzner

# Wireguard installieren
apt install -y wireguard

# Keys generieren
cd /etc/wireguard
umask 077
wg genkey | tee hetzner-private.key | wg pubkey > hetzner-public.key

# Keys anzeigen und notieren!
cat hetzner-private.key
cat hetzner-public.key
```

Config erstellen

```
nano /etc/wireguard/wg0.conf
```

Inhalt:

```
[Interface]
Address = 10.100.0.1/24
ListenPort = 51820
PrivateKey = <HETZNER_PRIVATE_KEY>

PostUp = sysctl -w net.ipv4.ip_forward=1
PostDown = sysctl -w net.ipv4.ip_forward=0

[Peer]
PublicKey = <HOMESERVER_PUBLIC_KEY>
AllowedIPs = 10.100.0.2/32
PersistentKeepalive = 25
```

Aktivieren

```
echo "net.ipv4.ip_forward=1" >> /etc/sysctl.conf  
sysctl -p
```

```
systemctl enable wg-quick@wg0  
systemctl start wg-quick@wg0  
systemctl status wg-quick@wg0
```

Revision #1

Created 2025-12-06 12:17:52 UTC by Denode

Updated 2025-12-06 12:17:52 UTC by Denode